

DETRGENT MIXING INSTRUCTION

pH:	11.7 -11.9
Caustic:	NO
Degreaser:	MEDIUM
Phosphates:	YES
Gloss Enhancers:	YES
Rinsing:	EXCELLENT
SuperFlo Polymer:	YES - HEAVY CONCENTRATIONS
Packaging:	One Drum Kit of base powder that will yield 55 gallons of liquid detergent concentrate. Some kits include a liquid additive



Mixing Instructions: Read and understand these instructions before starting to mix this product. Use warm water (never hot - not to exceed 120 degrees F). Warm water helps powders go into solution more easily. Hot water, on the other hand, will blow apart many of the surfactants utilized in the formulary process. It is possible to use cold water but additional manual agitation may be required. Use a clean poly drum; fill it approximately 50% full with warm water. Place the nozzle of a high-pressure washer close to the bottom of the drum and continue filling while adding the powder slowly. When the drum is 90% full all the powder should have been added. Continue filling until the drum is full. The result is 55 gallons of liquid concentrate that is now ready for use. If the kit contains a liquid additive slowing pour the additive in while mixing when the drum is $\frac{3}{4}$ full.

Dilutions: The amount you dilute on many factors and cannot be covered by one statement. The following guidelines are a starting point from which you should adjust. Chemical dilution rates need to be adjusted because of weather conditions, cleaning difficulty, washing method used, including PSI and whether or not you brush, and desired result. Remember that a typical downstream injector is already diluting the product approximately 1 part detergent to 9 parts water (10%) for most injectors or 2 parts product to 8 parts water (20%) with an Allison super suds sucker injector.

Starting Dilution: 1 part product to 50-65 parts water
(Salesmen will tell you very high dilution rates attempting to make you think their product is the best. Actual washing experience is the only way to determine what is right for you. Remember, detergent is much cheaper than labor.)

Make it a practice to always read and insist your employees read and understand the MSDS that accompanies this product.

CAUTION - Avoid Alkaline Shock: Any detergent product that is applied to a hot surface stands a chance of producing alkaline shock. The surface is hot - a strong solution of detergent is applied - the water evaporates from the product before you have a chance to rinse - all resulting in a dull, streaked or tarnished surface which is often irreversible. Cool the surface down with water first then apply the product. On real hot days turn off the burner and wash with cold water.

Gloss Enhancers have made us famous! Order up a drum pack and see why!